

Chapter 2
NIOS for DOS, MS Windows, and Windows95 Design

Introduction 10

DOS and Windows API Calls 10
- DOS Call Services 11
- File Services 11
- Memory Management Services 11
- Miscellaneous Services 12
- Protected-Mode Interrupt Management Services 12
- Screen Management Services 12
- V86 Callback Management Services 12
- V86 Interrupt Management Services 13
- V86 Mode Management Services 13
- Virtual Machine Management Services 13
- Services Available to Real-Mode DOS Applications 13
- Services Available to 16-bit MS Windows Applications 14
- Services Available to 32-bit MS Windows95 Applications . . . 14

Introduction

For each platform it supports, NIOS provides a set of platform-specific APIs for those client modules that are not OS-independent, such as API mappers. Applications that use these functions are not portable to other operating system platforms unless these calls are replaced by calls specific to the new operating system (e.g., DosCall might be replaced by Os2Call).

For the DOS/MS Windows environment, NIOS provides the functionality needed for protected-mode operation in a DOS environment, since DOS does not provide any protected-mode services.

Because these services also function when MS Windows is running, in many cases DOS/MS Windows specific code need not interface to the base OS, whether DOS or the MS Windows VMM directly.

DOS and Windows API Calls

Note that there are four different sets of API functions available. Which set the caller uses depends on the caller's environment.

- Real Mode DOS
- 16-bit Mode MS Windows
- 32-bit Mode MS Windows
- 32-bit NLMs

The following sections summarize these OS-dependent services grouped by functionality.

See Chapters 4 through 7 for detailed descriptions of each API listed below.

DOS Call Services

DosBeginUseDos Causes Ctrl-C, Ctrl-Break, and Int 24h to be ignored.
DosCall Assembly language API used to call DOS.
DosCallC C API used to call DOS.
DosCallWithDTA C API used to make DOS function calls that use the Disk Transfer Area.
DosCallUseCurrSDA Calls DOS using the current DOS SDA information.
DosCancelDosAvailEvent Cancels a previously scheduled DOS available event.
DosDeregisterUserCmd Deregisters a previously installed custom DOS command.
DosEndUseDos Restores the Ctrl-C, Ctrl-Break, and Int 24h vectors.
DosEnumerateUserCmds Determines which DOS custom commands have been registered.
DosInfoBlock Global structure containing misc. information about DOS. (In-DOS pointer, list of lists, etc.)
DosIsDosBusy Determines whether DOS is busy.
DosRegisterUserCmd Registers a new or replacement custom DOS command.
DosScheduleDosAvailEvent Schedules an event that fires when DOS is callable.

File Services

DosClose Closes a file.
DosCreate Creates a new file.
DosDelete Deletes a file.
DosDoesFileExist Determines if the specified file exists.
DosFlush Flushes all disk buffers.
DosGetFileSize Returns a file's size.
DosOpen Opens a file.
DosRead Reads data from a file.
DosRename Renames a file.
DosSearchForFile Searches for the specified file.
DosSeek Changes the current read/write/seek position for an opened file.
DosWrite Writes data to a file.

Memory Management Services

DosAMapFlat Assembly API used to convert a MS-Windows sel:off to a linear address.
DosCMapFlat C API used to convert a MS-Windows sel:off to a linear address.
DosConvGetInfo Returns the size of the largest available block of conventional memory.
DosConvMemAlloc Allocates a memory block below 1MB.
DosConvMemFree Deallocates a previously allocated conventional memory block.
DosSharedBufAlloc Allocates the shared DOS buffer provided by NIOS.
DosSharedBufFree Deallocates the shared DOS buffer.
DosSharedBufGetInfo Gets information about the shared DOS buffer.
Win16GetProcAddress Resolves the sel:off of an exported 16-bit Windows procedure.

Miscellaneous Services

DosBeginReentrantExec Used in special cases where an NLM needs to invoke a service that normally isn't callable at hardware interrupt time.
DosEndReentrantExec Ends a reentrant execution block.
DosGetExeContext Determines if current execution is in the foreground or is in the context of a hardware interrupt.
DosWinDebFlag Global flag set to 1 if Windows is active and a debugger is loaded.
DosWinFlag Global flag that is non-zero when enhanced-mode Windows is active.

Protected-Mode Interrupt Management Services

DosHookPMInterrupt Installs a handler for the specified PM interrupt.
DosUnHookPMInterrupt Deinstalls a PM interrupt handler.
DosHookExceptionInterrupt Installs a handler for a specific processor exception interrupt.
DosUnHookExceptionInterrupt Deinstalls a handler for an exception interrupt.
WinCallWhenPMIntReturns Obtains control on the back end of a current PM interrupt.
WinHookPMInt21 Hooks PM int 21 handlers in Windows.
WinUnHookPMInt21 Unhooks PM int 21 handlers in Windows.

Screen Management Services

DosVid16DeregisterGuiCB Cancels a previously registered GUI callback.
DosVid16RegisterGuiCB Sets the address of the current GUI callback.
DosVidCallWhenPopupOk Schedules an event to fire when the system can display a popup.
DosVidCheckKey Determines if a key is waiting in the keyboard buffer.
DosVidCursorSet Positions the cursor to the specified x,y coordinate in popup.
DosVidEmptyTypeAhead Empties the keyboard typeahead buffer.
DosVidGetKey Waits for a key press and returns the key value.
DosVidGetPopupInfo Obtains infomation about active popup.
DosVidIsPopupOk Determines if context allows display of popup message.
DosVidPopup Displays a popup message on the screen.
DosVidPopupExt Displays a popup with title, subtitle, prompt, and message text.
DosVidRestoreScreen Restores a portion of the screen from a dynamically allocated buffer.
DosVidSaveScreen Saves a portion of the screen to a dynamically allocated buffer.
DosVidSoundBell Rings the bell once.
DosVidStdOut Displays the specified prefix and message using DOS STDOUT.
DosVidWriteToPopup Writes a string to x,y position in popup.

V86 Callback Management Services

DosAllocV86Callback Allocates a V86 callback address.
DosFreeV86Callback Deallocates a previously allocated V86 callback.

V86 Interrupt Management Services

DosRegisterV86Int2F	Installs a handler for a specific Int 2F AH value.
DosDeregisterV86Int2F	Deinstalls an Int 2F handler.
DosHookV86Interrupt	Installs a hanndler for the specified V86 interrupt.
DosUnHookV86Interrupt	Deinstalls a V86 interrupt handler.
DosCallWhenV86IntReturns	Used to gain control on the back end of a V86 interrupt.

V86 Mode Management Services

DosBeginNestExec	Allocates a new ClientRegStruc for nested V86 execution.
DosEndNestExec	Deallocates a ClientRegStruc that was used for nested V86 execution.
DosBeginNestExecWithCrs	Sets up a nested V86 execution block using the provided ClientRegStruc. ("C" callable.)
DosEndNestExecWithCrs	Ends a nested V86 execution block. ("C" callable.)
DosExecuteV86FarCall	Calls a V86 procedure with a far return stack frame.
DosExecuteV86Int	Executes the specified V86 interrupt.
DosFastExecuteFarRet	Macro that simulates a V86 far return instruction.
DosFastExecutePop	Macro that simulates a V86 pop instruction.
DosFastExecutePush	Macro that simulates a V86 push instruction.
DosExecuteIRet	Simulates a V86 iret instruction.
DosExecuteFarRet	Simulates a V86 far return instruction.
DosExecutePop	Simulates a V86 pop instruction.
DosExecutePush	Simulates a V86 push instruction.

Virtual Machine Management Services

DosGetCurrVmHandle	Returns a pointer to the current VM control block.
DosGetNextVmHandle	Allows enumeration of existing VM control blocks.
DosVmIdToVmCbTable	Global table used to obtain the VM control block for a given VM Id.

Services Available to Real-Mode DOS Applications

Get NIOS Real Mode API	Returns API entry points used to access NIOS and other NLMs.
DosNiosFarCallHandler	Real-mode entry point for invoking NIOS functions.
DosInvokeRegNlmApiHandler	Invokes an exported NLM function that uses a register-based calling convention.
DosInvokeCNlmApiHandler	Invokes an exported NLM function that uses C calling conventions.
RM_NIOS_BEGIN_USE_API	Determines the 32-bit flat linear address of specified server NLM API name.
RM_NIOS_COPY_MEM	Copies data from a memory buffer above 1MB to a V86 mode buffer.
RM_NIOS_COPY_STRING	Copies string pointed to by pmBuffer into specified 16-bit seg:off buffer.
RM_NIOS_END_USE_API	Signals that the DOS application is done using the specified server NLM API.

RM_NIOS_MAP	Converts a seg:off value to a linear address and locks the memory.
RM_NIOS_UNMAP	Potentially unlocks a previously-mapped V86 mode buffer.

Services Available to 16-bit MS Windows Applications

Get NIOS Windows 16-bit Mode API	Accesses the NIOS APIs available to 16-bit Windows applications.
Win16InvokeRegNlmApiHandler	Invokes an exported NLM function that uses a register-based calling convention.
Win16InvokeCNlmApiHandler	Invokes an exported NLM function that uses C calling conventions.
Win16LoadModule	Loads an NLM.
Win16NiosFarCallHandler	Protected-mode entry point for invoking NIOS functions.
Win16UnloadModule	Unloads an NLM.
PM16_NIOS_BEGIN_USE_API	Returns the 32-bit flat linear address of the specified server NLM API name.
PM16_NIOS_COPY_MEM	Copies data from a linear address into the specified selector's offset buffer.
PM16_NIOS_COPY_STRING	Copies string from a linear address into the specified selector's offset buffer.
PM16_NIOS_END_USE_API	Signals that the application is done with the specified server NLM API function.

Services Available to 32-bit MS Windows95 Applications

Win32InvokeCNlmApi	Calls an exported NLM function that uses the "C" calling conventions.
Win32LoadModule	Loads an NLM for Win32 applications.
Win32NiosFarCall	Invokes NIOS services for Win32 applications.
Win32UnloadModule	Unloads an NLM for Win32 applications.
WIN32_NIOS_BEGIN_USE_API	Determines the 32-bit linear address of the specified NLM API name.
WIN32_NIOS_COPY_MEM	Copies the contents of the memory at the specified Ring 0 linear address into a Ring 3 buffer.
WIN32_NIOS_COPY_STRING	Copies the string pointed to by the Ring 0 pmBuffer address into a Ring 3 application buffer.
WIN32_NIOS_END_USE_API	Signals that the application is no longer going to use the specified NLM API function.
WIN32_NIOS_MAP	Converts the specified linear address local of a calling Win32 process into a globally accessible linear address.
WIN32_NIOS_UNMAP	Unlocks the application memory block and destroys the global linear range alias created through WIN32_NIOS_MAP.