

Chapter 6
NIOS APIs for MS Windows

Get NIOS Windows 16-Bit Mode API 152
Win16InvokeRegNlmApiHandler 153
Win16InvokeCNlmApiHandler 154
Win16LoadModule 155
Win16NiosFarCallHandler 158
Win16UnloadModule 159
PM16_NIOS_BEGIN_USE_API 161
PM16_NIOS_COPY_MEM 162
PM16_NIOS_COPY_STRING 163
PM16_NIOS_END_USE_API 164

Get NIOS Windows 16-Bit Mode API

Description

Use the following steps to access the NIOS APIs available to 16-bit MS Windows applications. These APIs provide, among other things, a method to invoke most exported NLM APIs from a 16-bit Windows application.

Locate the NIOS 16-bit Windows application interfaces by issuing an Int 2Fh as shown below. If AX returns set to 0000h then the API entry points are available.

On entry:

ax 0D8C3h

On return:

ax 0000h (NIOS is present)

bx Version of loaded NIOS module

bh has major version, bl has minor version

esi Sel:Off of NIOS far call handler (refer to **Win16NiosFarCallHandler** for more information)

ecx Sel:Off of NIOS function used to invoke "C" callable NLM functions (refer to **Win16InvokeCNlmApiHandler** for more information)

edx Sel:Off of NIOS function used to invoke register-based NLM functions (refer to **Win16InvokeRegNlmApiHandler** for more information)

All other registers preserved

See Also

Win16NiosFarCallHandler
Win16InvokeRegNlmApiHandler
Win16InvokeCNlmApiHandler

See Also

Win16InvokeRegNlmApiHandler

Description

This function is used by 16-bit Windows applications to call (invoke) exported NLM functions that use register-based calling conventions.

Assumes

apiAddress Pushed onto the stack
eax,ebx,ecx,edx,esi,edi,ebp
Set up as specified for the NLM API

Returns

General purpose registers set up as defined by NLM API
All segment registers are preserved
apiAddress is removed from stack

Remarks

Use the procedure outlined in "Get NIOS Windows 16-Bit Mode API" to get the **Win16InvokeRegNlmApiHandler** far call address.

Data pointer parameters passed to asynchronous NLM APIs must typically be page-locked by the application (for example, GlobalPageLock).

See Also

Get NIOS Windows 16-Bit Mode API
Win16InvokeCNlmApiHandler

Win16InvokeCNlmApiHandler

Description

16-bit MS Windows applications use this function to call (invoke) exported NLM functions that use "C" calling conventions.

Syntax

```
(*Win16InvokeCNlmApiHandler)(
    UINT32    apiAddress,
    UINT32    apiParmCount,
    ...);
```

Parameters

apiAddress Address of NLM API to invoke. Use **PM16_NIOS_BEGIN_USE_API** to get this value.

apiParmCount Number of UINT32 stack parameters needed for call. This value defines the number of UINT32 values that need to be copied from the application's stack onto the Ring-0 protected-mode stack prior to invoking the specified NLM API.

... Parameters to NLM API.

Returns

Defined by NLM API
UINT32 values are returned in registers DX:AX

Remarks

Use the procedure outlined in "Get NIOS Windows 16-Bit Mode API" to get the **Win16InvokeCNlmApiHandler** far call address.

Data pointer parameters passed to asynchronous NLM APIs must typically be page-locked by the application (for example, GlobalPageLock).

See Also

Get NIOS Windows 16-Bit Mode API
Win16InvokeRegNlmApiHandler

Win16LoadModule

Description

Called by 16-bit MS Windows applications to load an NLM.

Syntax

```
UINT32
Win16LoadModule(
    UINT32          loadOptions,
    UINT8       FAR16  *modulePathSpec,
    UINT8       FAR16  *commandLine,
    UINT32          nlmFileOffset,
    modHandle       *retModHandle,
    void            (FAR16  *msgHandler)(
                        modHandle    module,
                        UINT8        *prefix,
                        UINT8        *msg) );
```

Parameters

loadOptions Bits defining load styles. All undefined bits must be set to zero.

LOPTION_DEBUG_INIT
Executes an Int 1 before the loader invokes the module's initialization routine.

LOPTION_ERROR_MSGS
Standard output error messages are enabled.

LOPTION_BANNER_MSGS
Standard output sign on messages are enabled.

modulePathSpec Module [path\]name to load (with extension).

commandLine Pointer to any parameters that will be passed to the loading module. This is an ASCIIZ string.

nlmFileOffset Offset from the start of the modulePathSpec file where the NLM image starts. This will typically be zero for straight NLM files.

retModHandle Pointer to a module handle that will be set to the newly loaded module's handle on success. If NULL, the module handle will not be returned.

msgHandler Pointer to function which will be called when a text message is displayed during the load process. Parameters to this function are flat linear addresses; therefore the handler must either map a selector to them or use the appropriate NIOS functions to copy the memory.

Returns

LOADER_SUCCESS
Module was loaded successfully

LOADER_NO_LOAD_FILE
Open load file failed

LOADER_IO_ERROR
IO file error during read

LOADER_INSUFFICIENT_MEMORY
Not enough memory to load module

LOADER_INVALID_MODULE
Invalid NLM module

LOADER_UNDEFINED_EXTERN
Referenced undefined external item

LOADER_DUPLICATE_PUBLIC
Exported public is already defined

LOADER_NO_MSG_FILE
Open message file failed

LOADER_INVALID_MSG_MODULE
Message file is malformed

LOADER_MODULE_ALREADY_LOADER
Module cannot be loaded more than once

LOADER_BAD_REENTRANT_MODULE

Reentrant load failed because the module is not the same version as the first module

LOADER_MODULE_INIT_FAILED
Module failed to initialize

LOADER_LOAD_REFUSED
A loaded NLM refuses to allow this NLM to load

Remarks

All pointer parameters are passed in as selector:offset.

Windows applications needing to load an NLM typically will use this function instead of **NiosLoadModule**, since they will want to obtain text output messages from the NLM and loader while the load is taking place.

It is possible to invoke **NiosLoadModule** with the LOPTION_ERROR_MSGS set to zero from an MS Windows application, since this causes a silent load to take place.

See Also

Win16NiosFarCallHandler

Description

This function is invoked by 16-bit Windows applications using the address obtained using the procedure outlined in Get NIOS Windows 16-Bit Mode API.

Syntax

```
#include <nlmapi.h>

UINT32
(*Win16NiosFarCallHandler)(
    UINT32    function,
    ...);
```

Parameters

function One of the following values:

```
PM16_NIOS_BEGIN_USE_API    equ    00000000h
PM16_NIOS_END_USE_API      equ    00000001h
PM16_NIOS_COPY_MEM         equ    00000002h
PM16_NIOS_COPY_STRING      equ    00000003h
```

... Other parameters as needed

Returns

Values specific to each function
0x80000000 Invalid function request value

Remarks

Note that 32-bit return values are returned in registers DX:AX.

See Also

Win16UnloadModule

Description

Called by 16-bit MS Windows applications to unload an NLM.

Syntax

```
UINT32
Win16UnloadModule(
    modHandle   modHand,
    UINT32      unloadOptions,
    void        (FAR16  *msgHandler)(
                    modHandle    module,
                    UINT8        *prefix,
                    UINT8        *msg) );
```

Parameters

modHand — Handle of module to unload. This is a flat linear address of a module handle for the NLM to unload.

unloadOptions — Bits defining unload options. All undefined bits must be set to zero.

UOPTION_ERROR_MSGS
Standard output error messages

msgHandler — Pointer to function which will be called when a text message is displayed during the unload process. Parameters to this function are flat linear addresses; therefore the handler must either map a selector to them or use the appropriate NIOS functions to copy the memory.

Returns

UNLOAD_SUCCESS
Module was unloaded

UNLOAD_MODULE_FORBIDS_UNLOAD
Module does not allow unload

UNLOAD_MODULE_BEING_REFERENCED
Another module is using this module

UNLOAD_INVALID_MODULE_HANDLE
Module handle is invalid

UNLOAD_RESOURCES_NOT_FREED
Module did not free resources

UNLOAD_MODULE_CANT_UNLOAD_NOW
Module is temporarily unable to unload

UNLOAD_UNLOAD_REFUSED
A loaded NLM refuses to allow this NLM to load

Remarks All pointer parameters are passed in as selector:offset.

See Also

PM16_NIOS_BEGIN_USE_API

Description

Determines the 32-bit flat linear address of the specified NLM API name. The returned address can then be used with either the **Win16InvokeCNlmApiHandler** or the **Win16InvokeRegNlmApiHandler** far call handlers to actually invoke the NLM function from a 16-bit MS Windows application.

Syntax

```
UINT32
(*Win16NiosFarCallHandler)(
    UINT32    PM16_NIOS_BEGIN_USE_API,
    UINT8     FAR16 *apiName);
```

Parameters

apiName Name of the API you would like to call. This is a case-insensitive ASCIIZ string, for example, "CNWIpxSendPacket".

Returns

0	API does not exist
!0	Linear address of API

Remarks

This function records a dependency for the NLM module in which the API function exists, so it is important that the MS Windows application use **PM16_NIOS_END_USE_API** before the application terminates.

See Also

PM16_NIOS_END_USE_API

PM16_NIOS_COPY_MEM

Description

Copies *length* bytes of the memory at the specified protected-mode linear address into the specified 16-bit sel:off buffer.

Syntax

```
void
(*Win16NiosFarCallHandler)(
    UINT32    PM16_NIOS_COPY_MEM,
    void      FAR16 *destBuffer,
    UINT32    pmBuffer,
    UINT32    length);
```

Parameters

destBuffer Pointer to sel:off buffer to which to copy

pmBuffer Linear address of protected-mode buffer from which to copy

length Number of bytes to copy

Returns

Nothing

Remarks

See Also

PM16_NIOS_COPY_STRING

Description

Copies the string pointed to by *pmBuffer* into the specified 16-bit sel:off buffer.

Syntax

```
void
(*Win16NiosFarCallHandler)(
    UINT32    PM16_NIOS_STRING,
    void      FAR16 *destBuffer,
    UINT32    pmBuffer);
```

Parameters

destBuffer Pointer to sel:off buffer to copy to

pmBuffer Linear address of string

Returns

Nothing

Remarks

See Also

PM16_NIOS_END_USE_API

Description

Signals that the MS Windows application is no longer going to use the specified NLM API function. This deletes the dependency that was previously created using PM16_NIOS_BEGIN_USE_API.

Syntax

```
void
(*Win16NiosFarCallHandler)(
    UINT32    PM16_NIOS_END_USE_API,
    UINT32    apiLinAddress);
```

Parameters

apiLinAddress Linear address of NLM API function

Returns

Nothing

Remarks

See Also

PM16_NIOS_BEGIN_USE_API
NE_WIN_VM_SUSPEND